
FlyUX
NO UPCOMING TRIP
Add a trip
Book flights
Tickets
Book
Help
More
By default, area populated with already booked trips and details.
If no trip has been booked, show empty template with message: *No upcoming trip*.
On selection, user brought to 'Add a trip' screen.
On selection, user brought to 'Book flights' screen. See '02. Flight search' page.
On selection, user brought to 'Help' screen.
On selection, display of a hamburger menu with more sections.



- Returns to '01. Start screen'.
- Data previously entered saved.

- Returns to '01. Start screen'.
- Dialogue box if fields filled in: *Are you sure you want to cancel flight search and return to start screen?*

On selection, user brought to '02. Flight search - select airport' screen (Departure).

On selection, user brought to '02. Flight search - select airport' screen (Arrival).

On selection, user brought to '02. Flight search - select dates' screen.

On selection, user brought to '02. Flight search - add passengers' screen.



- Toggle by default on 'Return'
- On 'One-way' selection, 'Return' field is hidden and 'Departure' field spreads.

Inactive until following fields filled in:
- From
- To
- Departure on
- Return on (if return)
- Passengers: at least '1'

On selection, user brought to '03. Flight results' screen.



- Returns to '02. Flight search' screen.
- Data previously entered saved.
- Departure airport field by default state.

- Returns to '01. Start screen'.
- Dialogue box: *Are you sure you want to cancel flight search and return to start screen?*

- Blank field
- On selection, highlight field. Have cursor in selected state.
- Use standard keyboard type.

- Display airport names below based on first letters typed in searc field. Works from 1 letter on.
- By default, airports displayed based on previous searches.
- Each option can be clicked on.
- If country name is typed in, display all airports of that country.
- On selection, user brought to '02. Flight search' screen, with departure airport field updated.



- Returns to '02. Flight search' screen.
- Data previously entered saved.
- Arrival airport field by default state.

- Returns to '01. Start screen'.
- Dialogue box: *Are you sure you want to cancel flight search and return to start screen?*

- Blank field
- On selection, highlight field. Have cursor in selected state.
- Use standard keyboard type.

- Display airport names below based on first letters typed in searc field. Works from 1 letter on.
- By default, airports displayed based on previous searches.
- Each option can be clicked on.
- If country name is typed in, display all airports of that country.
- On selection, user brought to '02. Flight search' screen, with arrival airport field updated.



- Returns to '02. Flight search' screen.
- Data previously entered saved.
- Date fields by default state.

- Returns to '01. Start screen'.
- Dialogue box: *Are you sure you want to cancel flight search and return to start screen?*

By default, blank fields.

- Highlight available dates from today's date until last based on flight schedule.
- Display first months. Rest to be scrolled down.
- Available dates only active.

Inactive until following fields filled:
- Departure on
- Return on (if return added)



- Highlight when date selected.
- Populate 'Departure on' field when date selected with the selected date (1).

- Highlight when date selected.
- Highlight of length of stay as soon as return date selected
- Populate 'Return on' field when date selected with the selected date (2).

On selection, user brought to '02. Flight search' with updated date fields.



- Returns to '02. Flight search' screen.
- Data previously entered saved.
- Number of passengers stays by default '1 adult'.

- Returns to '01. Start screen'.
- Dialogue box: *Are you sure you want to cancel flight search and return to start screen?*

- Min. 1 adult.
- Max. 9 passengers in total.
- Children and infants only if 1 adult at least.
- Inactive or active sign to fulfill requirements as indicated above.

On selection, user brought to '02. Flight search' with updated number of passengers.



- Returns to '02. Flight search' screen.
- Data previously entered saved.

- Returns to '01. Start screen'.
- Dialogue box: *Are you sure you want to cancel flight search and return to start screen?*

By default, only direct flights displayed. If no direct flights available, show message and allow display of indirect flights.

- On selection, panel animates to expand to open state. See '03. Flight results - fare'.
- Animation to last 250 miliseconds.

- Date picker
- Date selected highlighted; other greyed out but active
- Slide left or right to select more dates. Once selected, update of selected date and update of flight results.
- Selected date always in the center



Always display three fares:
- if fare not available anymore, display inactive button with 'Sold out'
- if not, active button

On selection, highlight box and update price.

- Hidden until fare is selected.
- On selection, user brought to inbound flight selection or '03. Flight results - your selection' depending on stage.

- Returns to '03. Flight results' (inbound flight selection) screen.
- Data previously entered saved.

- Returns to '01. Start screen'.
- Dialogue box: *Are you sure you want to cancel flight search and return to start screen?*

On selection, user brought to '05. Passenger details' screen.



- On selection, panel animates to expand to open state. See below.
- Animation to last 250 miliseconds.



- On selection, panel animates to collapse to closed state. See below.
- Animation to last 250 miliseconds.

Active box to cancel extra immediately and update price and selection. On selection, option slides to the left and 'Delete' button appears.



- Returns to '03. Flight results - your selection' screen.
- Data previously entered saved.

- Returns to '01. Start screen'.
- Dialogue box: *Are you sure you want to cancel flight search and return to start screen?*

- On selection, highlight field.
- Input type: standard keyboard
- On type, remove hint text.
- Special characters or numbers not accepted.
- Validation occurs when type confirmed, when input is empty. Error message: Please enter valid name.

- On selection, highlight field.
- Input type: date
- On type, remove hint text.
- Validation occurs when type confirmed, when input does not match date format. Error message: *Please enter valid date.*

- On selection, highlight field.
- Input type: email
- On type, remove hint text.
- Validation occurs when type confirmed, when input does not match standard email format. Error message: *Please enter valid email address.*
- Both fields have to be filled in identically. Error message: *Please enter same email address.*

On selection, user brought to '05. Passenger details - add luggage' screen.

On selection, user brought to seat selection screen.

Inactive until following fields filled in and validated for all passengers:
- First name
- Last name
- Date of birth
- Email address
- Confirm email address

On selection, user brought to payment screen. See '06. Payment'.



- Toggle by default on 'Passenger 1'
- Once first name is filled in, name in toggle is updated.
- On selection, input fields and extra selection below are displayed for the selected passenger.
- Data already entered for other passenger saved.

05. Passenger details - add luggage

04.12.2019



- Returns to '05. Passenger details' screen.
- Data previously entered saved.
- Number of luggage stays as per default.

- Returns to '01. Start screen'.
- Dialogue box: *Are you sure you want to cancel flight search and return to start screen?*

- Active boxes.
- On selection, highlight box.

On selection, user brought to '05. Passenger details' screen.



- Returns to '05. Passenger details' screen.
- Data previously entered saved.

- Returns to '01. Start screen'.
- Dialogue box: *Are you sure you want to cancel flight booking and return to start screen?*

- On selection, panel animates to expand to open state. See below.
- Animation to last 250 miliseconds.



- On selection, panel animates to collapse to closed state. See below.
- Animation to last 250 miliseconds.

On selection, highlight box.

Inactive until payment method has been selected.

On selection, user brought to '06. Payment - enter details' screen.

04. Payment

04.12.2019



- Returns to (1) Flight selection - summary page and to (2) Passenger details.
- Data saved

- Returns to Passenger details page.
- Data saved

- On selection, panel animates to expand to open state. See '04. Payment - choose method' page.
- Animation to last 250 miliseconds.

Inactive until following fields filled in and validated :
- Card number
- Name on card
- Expiry date
- CVC

- On selection, user brought to confirmation page. See '05. Confirmation page' page.



- Returns to '06. Payment' screen.
- Data previously entered saved.

- Returns to '01. Start screen'.
- Dialogue box: *Are you sure you want to cancel flight booking and return to start screen?*

- On selection, highlight field.
- Input type: number
- On type, remove hint text.
- On type, chunk numbers in the given format.
- Max. characters: 16
- Validation occurs when type confirmed, when input does not match date format. Error message: *Please enter valid card number.*

- On selection, highlight field.
- Input type: standard keyboard
- On type, remove hint text.
- Special characters or numbers not accepted.
- Validation occurs when type confirmed, when input is empty. Error message: *Please enter valid name.*

- On selection, highlight field.
- Input type: date
- Max. characters: 4
- Validation occurs when type confirmed, when input does not match date format. Error message: *Please enter valid expiry date.*

- On selection, highlight field.
- Input type: number
- On type, remove hint text.
- Validation occurs when type confirmed, when input does not match format. Error message: *Please enter valid CVC.*
- Max. characters: 3

Inactive until following fields filled in and validated:
- Card number
- Name on card
- Expiry date
- CVC

On selection, user brought to confirmation screen. See '05. Confirmation screen'.



- Returns to '01. Start screen'.
- No dialogue box

On selection, trip details saved into the app under 'Tickets' and on the start screen.

On selection, user brough to 'create an account' screen. Hidden if user already logged in.



- Returns to '01. Start screen'.
- Data previously entered saved.

- Returns to '01. Start screen'.
- Dialogue box if fields filled in: *Are you sure you want to cancel flight search and return to start screen?*

On selection, user brought to '02. Flight search - select airport' screen (Departure).

On selection, user brought to '02. Flight search - select airport' screen (Arrival).

On selection, user brought to '02. Flight search - select dates' screen.

On selection, user brought to '02. Flight search - add passengers' screen.



- Toggle by default on 'Return'
- On 'One-way' selection, 'Return' field is hidden and 'Departure' field spreads.

Inactive until following fields filled in:
- From
- To
- Departure on
- Return on (if return)
- Passengers: at least '1'

On selection, user brought to '03. Flight results' screen.